

Oracle® Solaris Cluster Data Service for Network File System (NFS) Guide

ORACLE®

Part No: E39653
July 2014, E39653-01

Copyright © 2000, 2014, Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

U.S. GOVERNMENT END USERS. Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information on content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

Copyright © 2000, 2014, Oracle et/ou ses affiliés. Tous droits réservés.

Ce logiciel et la documentation qui l'accompagne sont protégés par les lois sur la propriété intellectuelle. Ils sont concédés sous licence et soumis à des restrictions d'utilisation et de divulgation. Sauf disposition de votre contrat de licence ou de la loi, vous ne pouvez pas copier, reproduire, traduire, diffuser, modifier, breveter, transmettre, distribuer, exposer, exécuter, publier ou afficher le logiciel, même partiellement, sous quelque forme et par quelque procédé que ce soit. Par ailleurs, il est interdit de procéder à toute ingénierie inverse du logiciel, de le désassembler ou de le décompiler, excepté à des fins d'interopérabilité avec des logiciels tiers ou tel que prescrit par la loi.

Les informations fournies dans ce document sont susceptibles de modification sans préavis. Par ailleurs, Oracle Corporation ne garantit pas qu'elles soient exemptes d'erreurs et vous invite, le cas échéant, à lui en faire part par écrit.

Si ce logiciel, ou la documentation qui l'accompagne, est concédé sous licence au Gouvernement des Etats-Unis, ou à toute entité qui délivre la licence de ce logiciel ou l'utilise pour le compte du Gouvernement des Etats-Unis, la notice suivante s'applique:

U.S. GOVERNMENT END USERS. Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

Ce logiciel ou matériel a été développé pour un usage général dans le cadre d'applications de gestion des informations. Ce logiciel ou matériel n'est pas conçu ni n'est destiné à être utilisé dans des applications à risque, notamment dans des applications pouvant causer des dommages corporels. Si vous utilisez ce logiciel ou matériel dans le cadre d'applications dangereuses, il est de votre responsabilité de prendre toutes les mesures de secours, de sauvegarde, de redondance et autres mesures nécessaires à son utilisation dans des conditions optimales de sécurité. Oracle Corporation et ses affiliés déclinent toute responsabilité quant aux dommages causés par l'utilisation de ce logiciel ou matériel pour ce type d'applications.

Oracle et Java sont des marques déposées d'Oracle Corporation et/ou de ses affiliés. Tout autre nom mentionné peut correspondre à des marques appartenant à d'autres propriétaires qu'Oracle.

Intel et Intel Xeon sont des marques ou des marques déposées d'Intel Corporation. Toutes les marques SPARC sont utilisées sous licence et sont des marques ou des marques déposées de SPARC International, Inc. AMD, Opteron, le logo AMD et le logo AMD Opteron sont des marques ou des marques déposées d'Advanced Micro Devices. UNIX est une marque déposée d'The Open Group.

Ce logiciel ou matériel et la documentation qui l'accompagne peuvent fournir des informations ou des liens donnant accès à des contenus, des produits et des services émanant de tiers. Oracle Corporation et ses affiliés déclinent toute responsabilité ou garantie expresse quant aux contenus, produits ou services émanant de tiers. En aucun cas, Oracle Corporation et ses affiliés ne sauraient être tenus pour responsables des pertes subies, des coûts occasionnés ou des dommages causés par l'accès à des contenus, produits ou services tiers, ou à leur utilisation.

Contents

Using This Documentation	7
1 Installing and Configuring HA for NFS	9
Overview of the Installation and Configuration Process for HA for NFS	10
Planning the HA for NFS Installation and Configuration	10
Service Management Facility Restrictions	10
NFSv3 Restrictions	11
Loopback File System Restrictions	11
ZFS Restrictions	11
Installing the HA for NFS Package	12
▼ How to Install the HA for NFS Package	12
Registering and Configuring HA for NFS	13
Setting HA for NFS Extension Properties	13
Tools for Registering and Configuring HA for NFS	14
▼ How to Register and Configure HA for NFS (c1setup)	14
▼ How to Register and Configure HA for NFS (Command Line Interface)	18
▼ How to Change Share Options on an NFS File System	23
▼ How to Dynamically Update Shared Paths on an NFS File System	25
How to Tune HA for NFS Method Timeouts	26
Configuring SUNW.HAStoragePlus Resource Type	27
▼ How to Set Up the HAStoragePlus Resource Type for an NFS-Exported UNIX File System Using the Command Line Interface	27
▼ How to Set Up the HAStoragePlus Resource Type for an NFS-Exported ZFS	30
Tuning the HA for NFS Fault Monitor	32
Fault Monitor Startup	32
Fault Monitor Stop	32
Operations of HA for NFS Fault Monitor During a Probe	32
Upgrading the SUNW.nfs Resource Type	35
Information for Registering the New Resource Type Version	35
Information for Migrating Existing Instances of the Resource Type	35

A HA for NFS Extension Properties	37
Index	41

Using This Documentation

- **Overview** – Provides information for installing and configuring the Oracle Solaris Cluster data services.
- **Audience** – Experienced system administrators with extensive knowledge of Oracle software and hardware.
- **Required knowledge** – Knowledge of the Oracle Solaris operating system, of Oracle Solaris Cluster software, and expertise with the volume manager software that is used with Oracle Solaris Cluster software.

This document is not to be used as a planning or presales guide.

Product Documentation Library

Late-breaking information and known issues for this product are included in the documentation library at <http://www.oracle.com/pls/topic/lookup?ctx=E39579>.

Access to Oracle Support

Oracle customers have access to electronic support through My Oracle Support. For information, visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info> or visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs> if you are hearing impaired.

Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program web site at <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

Feedback

Provide feedback about this documentation at <http://www.oracle.com/goto/docfeedback>.

Installing and Configuring HA for NFS

This chapter describes the steps to install and configure Oracle Solaris Cluster HA for Network File System (NFS) (HA for NFS) on your Oracle Solaris Cluster nodes.

Note - Install and configure this data service to run only in the global zone. This data service is not supported in non-global zones. For updated information about supported configurations of this data service, see [Oracle Solaris Cluster 4 Compatibility Guide](http://www.oracle.com/technetwork/server-storage/solaris-cluster/overview/solariscluster4-compatibilityguide-1429037.pdf) (<http://www.oracle.com/technetwork/server-storage/solaris-cluster/overview/solariscluster4-compatibilityguide-1429037.pdf>).

This chapter contains the following sections:

- [“Overview of the Installation and Configuration Process for HA for NFS” on page 10](#)
- [“Planning the HA for NFS Installation and Configuration” on page 10](#)
- [“Installing the HA for NFS Package” on page 12](#)
- [“Registering and Configuring HA for NFS” on page 13](#)
- [“Tuning the HA for NFS Fault Monitor” on page 32](#)
- [“Upgrading the SUNW.nfs Resource Type” on page 35](#)

You must configure HA for NFS as a failover data service. See [Chapter 1, “Planning for Oracle Solaris Cluster Data Services,”](#) in [“Oracle Solaris Cluster Data Services Planning and Administration Guide ”](#) and the [“Oracle Solaris Cluster Concepts Guide ”](#) document for general information about data services, resource groups, resources, and other related topics.

The NFS mount points that are placed under the control of the data service must be the same on all of the nodes that can master the disk device group that contains those file systems.

HA for NFS requires that all NFS client mounts be “hard” mounts.

No Oracle Solaris Cluster node may be an NFS client of a file system that is exported by HA for NFS and is being mastered on a node in the same cluster. Such cross-mounting of HA for NFS is prohibited. Use the cluster file system to share files among cluster nodes.

If Oracle Solaris Resource Manager is used to manage system resources allocated to NFS on a cluster, all HA for NFS resources which can fail over to a common cluster node must have the same Oracle Solaris Resource Manager project ID. This project ID is set with the `Resource_project_name` resource property.

Overview of the Installation and Configuration Process for HA for NFS

The following table lists the sections that describe the installation and configuration tasks.

TABLE 1-1 Task Map: Installing and Configuring HA for NFS

Task	For Instructions
Install HA for NFS packages	“How to Install the HA for NFS Package” on page 12
Set up and configure HA for NFS	“Registering and Configuring HA for NFS” on page 13
Tune the HA for NFS fault monitor	“Tuning the HA for NFS Fault Monitor” on page 32
Upgrade the SUNW.nfs resource type	“Upgrading the SUNW.nfs Resource Type” on page 35

Planning the HA for NFS Installation and Configuration

This section contains the information that you need to plan the installation and configuration of your HA for NFS.

Service Management Facility Restrictions

The following Service Management Facility (SMF) services are related to NFS.

- /network/nfs/cbd
- /network/nfs/mapid
- /network/nfs/server
- /network/nfs/rquota
- /network/nfs/client
- /network/nfs/status
- /network/nfs/nlockmgr

The HA for NFS data service sets the property `application/auto_enable` to `FALSE` and the property `startd/duration` to `transient` for three of these services.

- /network/nfs/server
- /network/nfs/status
- /network/nfs/nlockmgr

These property settings have the following consequences for these services.

- When services that depend on these services are enabled, these services are not automatically enabled.
- In the event of any failure, SMF does not restart the daemons that are associated with these services.
- In the event of any failure, SMF does not restart these services.

NFSv3 Restrictions

If you are mounting file systems on the cluster nodes from external NFS servers, such as NAS filers, and you are using the NFSv3 protocol, you cannot run NFS client mounts and the HA for NFS data service on the same cluster node. If you do, certain HA for NFS data-service activities might cause the NFS daemons to stop and restart, interrupting NFS services. However, you can safely run the HA for NFS data service if you use the NFSv4 protocol to mount external NFS file systems on the cluster nodes.

Loopback File System Restrictions

Do *not* use the loopback file system (LOFS) if both conditions in the following list are met:

- HA for NFS is configured on a highly available local file system.
- The automountd daemon is running.

If both of these conditions are met, LOFS must be disabled to avoid switchover problems or other failures. If only one of these conditions is met, it is safe to enable LOFS.

If you require both LOFS and the automountd daemon to be enabled, exclude from the automounter map all files that are part of the highly available local file system that is exported by HA for NFS.

ZFS Restrictions

If you are using ZFS as the exported file system, you must set the `sharenfs` property to `off`.

To set the `sharenfs` property to `off`, run the following command.

```
$ zfs set sharenfs=off file_system/volume
```

To verify if the `sharenfs` property is set to `off`, run the following command.

```
$ zfs get sharenfs file_system/volume
```

Installing the HA for NFS Package

If you did not install the HA for NFS package during your initial Oracle Solaris Cluster installation, perform this procedure to install the package.

▼ How to Install the HA for NFS Package

Perform this procedure on each cluster node where you want the HA for NFS software to run.

1. **On the cluster node where you are installing the data service package, assume the root role.**
2. **Ensure that the data service package is available from the configured publisher and that the `solaris` and `ha-cluster` publishers are valid.**

```
# pkg list -a ha-cluster/data-service/nfs
# pkg publisher
PUBLISHER                                TYPE    STATUS  P  LOCATION
solaris                                  origin  online  F  solaris-repository
ha-cluster                               origin  online  F  ha-cluster-repository
```

For information about setting the `solaris` publisher, see [“Adding, Modifying, or Removing Package Publishers”](#) in [“Adding and Updating Software in Oracle Solaris 11.2”](#).

Tip - Use the `-nv` options whenever you install or update to see what changes will be made, such as which versions of which packages will be installed or updated and whether a new BE will be created.

If you do not get any error messages when you use the `-nv` options, run the command again without the `-n` option to actually perform the installation or update. If you do get error messages, run the command again with more `-v` options (for example, `-nvv`) or more of the package FMRI pattern to get more information to help you diagnose and fix the problem. For troubleshooting information, see [Appendix A, “Troubleshooting Package Installation and Update,”](#) in [“Adding and Updating Software in Oracle Solaris 11.2”](#).

3. **Install the HA for NFS software package.**

```
# pkg install ha-cluster/data-service/nfs
```

4. **Verify that the package installed successfully.**

```
$ pkg info ha-cluster/data-service/nfs
```

Installation is successful if output shows that State is Installed.

5. **Perform any necessary updates to the Oracle Solaris Cluster software.**
For instructions on updating your software, see [Chapter 11, “Updating Your Software,”](#) in [“Oracle Solaris Cluster System Administration Guide”](#).

Registering and Configuring HA for NFS

This section describes how to register and configure HA for NFS.

Note - Other options also enable you to register and configure the data service. See [“Tools for Data Service Resource Administration”](#) in [“Oracle Solaris Cluster Data Services Planning and Administration Guide”](#) for details about these options.

Before you register and configure HA for NFS, run the following command to verify that the HA for NFS package, `ha-cluster/data-service/nfs`, is installed on the cluster.

```
# pkg info -l ha-cluster/data-service/nfs
```

If the package has not been installed, see [“Installing the HA for NFS Package”](#) on page 12 for instructions on how to install the package.

Setting HA for NFS Extension Properties

The sections that follow contain instructions for registering and configuring resources. For information about the HA for NFS extension properties, see [Appendix A, “HA for NFS Extension Properties”](#). The Tunable entry indicates when you can update a property.

To set an extension property of a resource, include the following option in the `clresource` command that creates or modifies the resource:

```
-p property=value
```

```
-p property
```

Identifies the extension property that you are setting.

```
value
```

Specifies the value to which you are setting the extension property.

You can also use the procedures in [Chapter 2, “Administering Data Service Resources,”](#) in [“Oracle Solaris Cluster Data Services Planning and Administration Guide”](#) to configure resources after the resources are created.

Tools for Registering and Configuring HA for NFS

Oracle Solaris Cluster provides the following tools for registering and configuring HA for NFS:

- **The `clsetup(1CL)` utility.** For more information, see “[How to Register and Configure HA for NFS \(clsetup\)](#)” on page 14.
- **Oracle Solaris Cluster maintenance commands** For more information, see “[How to Register and Configure HA for NFS \(Command Line Interface\)](#)” on page 18.

The `clsetup` utility provides a wizard for configuring HA for NFS. This wizard reduces the possibility for configuration errors that might result from command syntax errors or omissions. This wizard also ensures that all required resources are created and that all required dependencies between resources are set.

▼ How to Register and Configure HA for NFS (clsetup)

Perform this procedure during your initial set up of HA for NFS. Perform this procedure from one node only.

Note - The following instructions explain how to perform this operation by using the `clsetup` utility.

Before You Begin Before you start the HA for NFS wizard, ensure that the following prerequisites are met:

- Prerequisites for configuring a logical hostname resource are met.
- Prerequisites for configuring a highly available storage resource are met.
- The HA for NFS package is installed.

1. **Assume the `root` role on any cluster node.**
2. **Ensure that the `hosts` and `rpc` entries in the `/etc/nsswitch.conf` file are correct.**

The example output shows a configuration that uses the NIS external naming service.

- a. **Display the lookup entries for `hosts` and `rpc`.**

The following example shows the correct lookup entries.

```
# svccfg -s svc:/system/name-service/switch listprop config/host
hosts: cluster files [SUCCESS=return] nis
# svccfg -s svc:/system/name-service/switch listprop config/rpc
rpc: files nis
```

- For hosts, files must follow cluster and precede any directory or name service. This modification enables HA for NFS to fail over correctly in the presence of public network failures.

For rpc, files must precede any directory or name service. This configuration prevents timing-related errors for rpc lookups during periods of public network or name service unavailability.

b. If a lookup entry is not correct, set the correct lookups.

- For hosts:

```
# svccfg -s svc:/system/name-service/switch \
  setprop config/host = astring: \"cluster files [SUCCESS=return] nis\"
```

- For rpc:

```
# svccfg -s svc:/system/name-service/switch \
  setprop config/rpc = astring: \"files nis\"
```

3. Start the clsetup utility.

```
# clsetup
```

The clsetup main menu is displayed.

4. Select the option for Data Services and press Return.

The Data Services menu is displayed.

5. Select the option for configuring HA for NFS and press Return.

The clsetup utility displays the list of prerequisites for performing this task.

6. Verify that the prerequisites are met, and press Return.

The clsetup utility displays a list of all cluster nodes that are online.

7. Select the nodes where you require HA for NFS to run.

- **To accept the default selection of all listed nodes in an arbitrary order, type a and press Return.**
- **To select a subset of the listed nodes, type a comma-separated or space-separated list of the numbers that correspond to the nodes and press Return.**

Ensure that the nodes are listed in the order in which the nodes are to appear in the resource group's node list. The first node in the list is the primary node of this resource group.

- **To select all nodes in a particular order, type a comma-separated or space-separated ordered list of the numbers that correspond to the nodes and press Return.**

Ensure that the nodes are listed in the order in which the nodes are to appear in the resource group's node list. The first node in the list is the primary node of this resource group.
- 8. **To confirm your selection of nodes, type `d` and press Return.**

The `clsetup` utility displays a list of existing logical hostname resources on the cluster.
- 9. **You can choose any of the following options.**
 - **To use the existing logical hostname resource, select the option for the required logical hostname and press Return. Go to [Step 12](#).**
 - **To create a new logical hostname resource, type `c` and press Return. Go to [Step 10](#)**
- 10. **Type the logical hostname and press Return.**

The `clsetup` utility displays a list of existing logical hostname resources.
- 11. **Select the option for the logical hostname resource to be created and press Return.**

The `clsetup` creates the logical hostname resource.
- 12. **To confirm your selection of logical hostname resource, type `d` and press Return.**

The `clsetup` utility displays information about file system mount points.
- 13. **Press Return to continue.**

The `clsetup` utility displays the existing file system mount points.
- 14. **Select the file system mount points for HA for NFS data files.**
 - **To select a subset of the listed file system mount points, type a comma-separated or space-separated list of the numbers that correspond to the file system node point and press Return.**
 - **To select all file system mount points in a particular order, type a comma-separated or space-separated ordered list of the numbers that correspond to the file system mount points and press Return.**
- 15. **To confirm your selection of file system mount points, type `d` and press Return.**

The clsetup utility displays a screen where you can specify the path prefix for HA for NFS resource group.

16. Select the path prefix for HA for NFS resource group and press Return.

The clsetup utility displays a screen where you can change the share option for the file system mount point that the NFS server is sharing.

17. Select the share option and press Return.

The clsetup utility displays the share options for the selected mount points.

18. If you require a different name for any Oracle Solaris Cluster objects, change each name as follows.

a. Select the option for the name that you are changing and press Return.

The clsetup utility displays a screen where you can specify the new name.

b. At the New Value prompt, type the new name and press Return.

The clsetup utility returns you to the list of the names of the Oracle Solaris Cluster objects that the utility will create.

19. To confirm your selection of Oracle Solaris Cluster object names, type d and press Return.

The clsetup utility displays information about the Oracle Solaris Cluster configuration that the utility will create.

20. To create the configuration, type c and Press Return.

The clsetup utility displays a progress message to indicate that the utility is running commands to create the configuration. When configuration is complete, the clsetup utility displays the commands that the utility ran to create the configuration.

21. Press Return to continue.

The clsetup utility returns you to the Data Services Menu.

22. Type q and press Return.

The clsetup utility returns you to the Main Menu.

23. (Optional) Type q and press Return to quit the clsetup utility.

If you prefer, you can leave the clsetup utility running while you perform other required tasks before using the utility again. If you choose to quit clsetup, the utility recognizes your HA for NFS resource group when you restart the utility.

24. Determine whether the HA for NFS resource group and its resources are online.

Use the `clresourcegroup` command for this purpose. By default, the `clsetup` utility assigns the name `nfs-mountpoint-admin-rg` to the HA for NFS resource group.

```
# clresourcegroup status nfs-mountpoint-admin-rg
```

25. **If the HA for NFS resource group and its resources are *not* online, bring them online.**

```
# clresourcegroup online -eM nfs-rg
```

▼ How to Register and Configure HA for NFS (Command Line Interface)

Before You Begin ■ Verify that all the cluster nodes are online.

```
# clnode status
```

- Ensure that the `/etc/netmasks` file has IP-address subnet and netmask entries for all logical hostnames. If necessary, edit the `/etc/netmasks` file to add any missing entries.

1. **On a cluster member, assume the `root` role or assume a role that provides `solaris.cluster.admin` RBAC authorization.**
2. **Ensure that the `hosts` and `rpc` entries in the `/etc/nsswitch.conf` file are correct.**

The example output shows a configuration that uses the NIS external naming service.

- a. **Display the lookup entries for `hosts` and `rpc`.**

The following example shows the correct lookup entries.

```
# svccfg -s svc:/system/name-service/switch listprop config/host
hosts: cluster files [SUCCESS=return] nis
# svccfg -s svc:/system/name-service/switch listprop config/rpc
rpc: files nis
```

- For `hosts`, `files` must follow `cluster` and precede any directory or name service. This modification enables HA for NFS to fail over correctly in the presence of public network failures.

For `rpc`, `files` must precede any directory or name service. This configuration prevents timing-related errors for `rpc` lookups during periods of public network or name service unavailability.

- b. **If a lookup entry is not correct, set the correct lookups.**

- For `hosts`:

```
# svccfg -s svc:/system/name-service/switch \
setprop config/host = astring: \"cluster files [SUCCESS=return] nis\"
```

- For rpc:

```
# svccfg -s svc:/system/name-service/switch \
setprop config/rpc = astring: \"files nis\"
```

3. Create the *Pathprefix* directory.

Create a *Pathprefix* directory on the HA file system (cluster file system or highly available local file system). HA for NFS resources will use this directory to maintain administrative information.

You can specify any directory for this purpose. However, you must manually create a *Pathprefix* directory for each resource group that you create.

```
# mkdir -p Pathprefix-directory
```

4. Create a failover resource group to contain the NFS resources.

```
# clresourcegroup create [-n nodelist] -p Pathprefix=Pathprefix-directory resource-group
```

[-n nodelist]

Specifies an optional, comma-separated list of physical node names or IDs that identify potential masters. The order here determines the order in which the Resource Group Manager (RGM) considers primary nodes during failover.

-p Pathprefix=Pathprefix-directory

Specifies a directory that resources in this resource group will use to maintain administrative information. This is the directory that you created in [Step 3](#).

resource-group

Specifies the failover resource group.

5. Verify that you have added all your logical hostname resources to the name service database.

To avoid any failures because of name service lookups, verify that all IP addresses to hostname mappings that are used by HA for NFS are present in the server's and client's `/etc/inet/hosts` file.

6. (Optional) Customize the `nfsd` or `lockd` startup options.

Use the `sharectl` command to customize the `nfsd` and `lockd` options. For more information, see the [nfsd\(1M\)](#), [lockd\(1M\)](#), and [sharectl\(1M\)](#) man pages.

7. Add the desired logical hostname resources into the failover resource group.

You must set up a logical hostname resource with this step. The logical hostname that you use with HA for NFS *cannot* be a SharedAddress resource type.

```
# clreslogicalhostname create -g resource-group -h logical-hostname, ... [-N netiflist] lhresource
```

-g *resource-group*

Specifies the resource group that is to hold the logical hostname resources.

-h *logical-hostname, ...*

Specifies the logical hostname resource to be added.

-N *netiflist*

Specifies an optional, comma-separated list that identifies the IPMP groups that are on each node. Each element in *netiflist* must be in the form of *netif@node*. *netif* can be used as an IPMP group name, such as *sc_ipmp0*. The node can be identified by the node name or node ID, such as *sc_ipmp0@1* or *sc_ipmp@phys-schost-1*.

Note - If you require a fully qualified hostname, you must specify the fully qualified name with the -h option and you cannot use the fully qualified form in the resource name.

Note - Oracle Solaris Cluster does not currently support using the adapter name for *netif*.

8. From any cluster node, create the `SUNW.nfs` subdirectory.

Create a subdirectory called `SUNW.nfs` below the directory that the `Pathprefix` property identifies in [Step 4](#).

```
# mkdir Pathprefix-directory/SUNW.nfs
```

9. Create a `dfstab.resource` file in the `SUNW.nfs` directory that you created in [Step 8](#), and set up share options.

a. Create the `Pathprefix/SUNW.nfs/dfstab.resource` file.

This file contains a set of share commands with the shared path names. The shared paths should be subdirectories on a cluster file system.

Note - Choose a *resource* name suffix to identify the NFS resource that you plan to create in [Step 11](#). A good resource name refers to the task that this resource is expected to perform. For example, a name such as `user-nfs-home` is a good candidate for an NFS resource that shares user home directories.

b. Set up the share options for each path that you have created to be shared.

The format of this file is exactly the same as the format that is used in the `/etc/dfs/dfstab` file.

```
# share -F nfs [-o specific_options] [-d "description"] pathname
```

`-F nfs`

Identifies the file system type as `nfs`.

`-o specific_options`

Grants read-write access to all the clients. See the [share\(1M\)](#) man page for a list of options. Set the `rw` option for Oracle Solaris Cluster.

`-d description`

Describes the file system to add.

pathname

Identifies the file system to share.

Note - If you want to share multiple paths, the above `share` command need to be repeated for each path that you are sharing.

When you set up your share options, consider the following points.

- When constructing share options, do not use the `root` option, and do not mix the `ro` and `rw` options.
- Do not grant access to the hostnames on the cluster interconnect.
Grant read and write access to all the cluster nodes and logical hosts to enable HA for NFS monitoring to do a thorough job. However, you can restrict write access to the file system or make the file system entirely read-only. If you do so, HA for NFS fault monitoring can still perform monitoring without having write access.
- If you specify a client list in the `share` command, include all the physical hostnames and logical hostnames that are associated with the cluster. Also include the hostnames for all the clients on all the public networks to which the cluster is connected.
- If you use `net groups` in the `share` command, rather than names of individual hosts, add all those cluster hostnames to the appropriate `net group`.

The `share -o rw` command grants write access to all the clients, including the hostnames that the Oracle Solaris Cluster software uses. This command enables HA for NFS fault monitoring to operate most efficiently. See the following man pages for details:

- [share\(1M\)](#)
- [share_nfs\(1M\)](#)

10. Register the NFS resource type.

```
# clresourcetype register resource-type  
  
resource-type
```

Adds the specified resource type. For HA for NFS, the resource type is `SUNW.nfs`.

11. Create the NFS resource in the failover resource group.

```
# clresource create -g resource-group -t resource-type resource  
  
-g resource-group
```

Specifies the name of a previously created resource group to which this resource is to be added.

```
-t resource-type
```

Specifies the name of the resource type to which this resource belongs. This name must be the name of a registered resource type.

```
resource
```

Specifies the name of the resource to add, which you defined in [Step 9](#). This name can be your choice but must be unique within the cluster.

The resource is created in the enabled state.

12. Run the `clresourcegroup online -M resource-group` command to manage the resource group.

```
# clresourcegroup online -M resource-group
```

Example 1-1 Setting Up and Configuring HA for NFS

The following example shows how to set up and configure HA for NFS.

1. To create a logical host resource group and specify the path to the administrative files used by NFS (`Pathprefix`), the following command is run.

```
# clresourcegroup create -p Pathprefix=/global/nfs resource-group-1
```

2. To add logical hostname resources into the logical host resource group, the following command is run.

```
# clreslogicalhostname create -g resource-group-1 -h schost-1 lhresource
```

3. To make the directory structure contain the HA for NFS configuration files, the following command is run.

```
# mkdir -p /global/nfs/SUNW.nfs
```

4. To create the `dfstab.resource` file under the `nfs/SUNW.nfs` directory and set share options, the following command is run.

```
# share -F nfs -o rw=engineering -d "home dirs" /global/nfs/SUNW.nfs
```

Note - You also need to add this entry to the `dfstab.resource` file.

- To register the NFS resource type, the following command is run.

```
# clresourcetype register SUNW.nfs
```

- To create the NFS resource in the resource group, the following command is run.

```
# clresource create -g resource-group-1 -t SUNW.nfs r-nfs
```

The resource is created in the enabled state.

- To enable the resources and their monitors, manage the resource group, and switch the resource group into online state, the following command is run.

```
# clresourcegroup online -M resource-group-1
```

▼ How to Change Share Options on an NFS File System

If you use the `rw`, `rw=`, `ro`, or `ro=` options to the `share -o` command, NFS fault monitoring works best if you grant access to all the physical hosts or `netgroups` that are associated with all the Oracle Solaris Cluster servers.

If you use `netgroups` in the `sharecommand`, add all the Oracle Solaris Cluster hostnames to the appropriate `netgroup`. Ideally, grant both read access and write access to all the Oracle Solaris Cluster hostnames to enable the NFS fault probes to do a complete job.

Note - Before you change share options, read the [share_nfs\(1M\)](#) man page to understand which combinations of options are legal.

You can also modify the shared path and options dynamically without bringing offline the HA for NFS resource. See [“How to Dynamically Update Shared Paths on an NFS File System” on page 25](#).

To modify the share options on an NFS file system while the HA for NFS resource is offline, perform the following steps.

- On a cluster member, assume the `root` role or assume a role that provides `solaris.cluster.admin` RBAC authorization.**
- Turn off fault monitoring on the NFS resource.**

```
# clresource unmonitor resource
```

3. Test the new share options.

- a. Before you edit the `dfstab.resource` file with new share options, execute the new share command to verify the validity of your combination of options.**

```
# share -F nfs [-o specific_options] [-d "description"] pathname
```

`-F nfs`

Identifies the file system type as NFS.

`-o specific_options`

Specifies an option. You might use `rw`, which grants read-write access to all the clients.

`-d description`

Describes the file system to add.

`pathname`

Identifies the file system to share.

- b. If the new share command fails, immediately execute another share command with the old options.**

When the new command executes successfully, proceed to [Step 4](#).

4. Edit the `dfstab.resource` file with the new share options.

- a. To remove a path from the `dfstab.resource` file, perform the following steps in order.**

- i. Run the `unshare` command.**

```
# unshare -F nfs [-o specific_options] pathname
```

`-F nfs`

Identifies the file system type as NFS.

`-o specific_options`

Specifies the options that are specific to NFS file systems.

`pathname`

Identifies the file system that is made unavailable.

- ii. **From the `dfstab.resource` file, delete the share command for the path that you want to remove.**

```
# vi dfstab.resource
```

- b. **To add a path or change an existing path in the `dfstab.resource` file, verify that the mount point is valid, then edit the `dfstab.resource` file.**

5. **Enable fault monitoring on the NFS resource.**

```
# clresource monitor resource
```

▼ How to Dynamically Update Shared Paths on an NFS File System

You can dynamically modify the share command on an NFS file system without bringing offline the HA for NFS resource. The general procedure consists of modifying the `dfstab.resource` file for HA for NFS and then manually running the appropriate command, either the share command or the unshare command. The command is immediately effective, and HA for NFS handles making these paths highly available.

Ensure that the paths that are shared are always available to HA for NFS during failover so that local paths (on non-HA file systems) are not used.

If paths on a file system that is managed by HAStoragePlus are shared, the HAStoragePlus resource must be in the same resource group as the HA for NFS resource, and the dependency between them must be set correctly.

1. **Use the `cluster status` command to find out the node on which the HA for NFS resource is online.**
2. **On this node, run the `/usr/sbin/share` command to see the list of paths currently shared and determine the changes to make to this list.**
3. **To add a new shared path, perform the following steps.**
 - a. **Add the share command to the `dfstab.resource` file.**
HA for NFS shares the new path the next time it checks the file. The frequency of these checks is controlled by the `Thorough_Probe_Interval` property (by default 120 seconds).
 - b. **Run the share command manually to make the newly added shared path effective immediately.**

Running the command manually ensures that the shared paths are available to potential clients. HA for NFS detects that the newly added path is already shared and does not report an error.

4. **To unshare a path, perform the following steps.**
 - a. **Run the `dfmounts` command to ensure that no clients are currently using the path.**

Although a path can be unshared even if clients are using it, these clients would receive a stale file error handle and would need special care (forced unmount, or even reboot) to recover.
 - b. **Remove the `share` command from the `dfstab.resource` file.**
 - c. **Run the `unshare` command manually.**
5. **To modify options for an existing shared path, perform the following steps.**
 - a. **Modify the `dfstab.resource` file as needed.**
 - b. **Run the appropriate command (`share` or `unshare`) manually.**

How to Tune HA for NFS Method Timeouts

The time that HA for NFS methods require to finish depends on the number of paths that the resources share through the `dfstab.resource` file. The default timeout for these methods is 300 seconds.

As a general guideline, allocate 10 seconds toward the method timeouts for each path that is shared. Default timeouts are designed to handle 30 shared paths.

- If the number of shared paths is less than 30, do not reduce the timeout.
- If the number of shared paths exceeds 30, multiply the number of paths by 10 to compute the recommended timeout. For example, if the `dfstab.resource` file contains 50 shared paths, the recommended timeout is 500 seconds.

Update the following method timeouts if the number of shared paths is greater than 30.

- `Prenet_start_timeout`
- `Postnet_stop_timeout`
- `Start_timeout`
- `Stop_timeout`

- `Validate_timeout`
- `Update_timeout`
- `Monitor_Start_timeout`
- `Monitor_Stop_timeout`
- `Monitor_Check_timeout`

To change method timeouts, use the `clresource set` command, as in the following example.

```
% clresource set -p Prenet_start_timeout=500 resource
```

Configuring SUNW.HAStoragePlus Resource Type

HA for NFS is a disk-intensive data service. Therefore, you should configure the SUNW.HAStoragePlus resource type for use with this data service. For an overview of the SUNW.HAStoragePlus resource type, see [“Understanding HAStoragePlus”](#) in [“Oracle Solaris Cluster Data Services Planning and Administration Guide”](#).

The procedure for configuring the SUNW.HAStoragePlus resource type depends on the type of the file system that NFS is sharing. For more information, see the following sections:

- [“How to Set Up the HAStoragePlus Resource Type for an NFS-Exported UNIX File System Using the Command Line Interface”](#) on page 27
- [“How to Set Up the HAStoragePlus Resource Type for an NFS-Exported ZFS”](#) on page 30

▼ How to Set Up the HAStoragePlus Resource Type for an NFS-Exported UNIX File System Using the Command Line Interface

The HAStoragePlus resource type synchronizes the startups between resource groups and disk device groups. The HAStoragePlus resource type has an additional feature to make a local file system highly available. For background information about making a local file system highly available, see [“Enabling Highly Available Local File Systems”](#) in [“Oracle Solaris Cluster Data Services Planning and Administration Guide”](#). To use both of these features, set up the HAStoragePlus resource type.

Note - These instructions explain how to use the HAStoragePlus resource type with the UNIX file system (UFS). For information about using the HAStoragePlus resource type with the Sun QFS file system, see your Sun QFS documentation.

The following example uses a simple NFS service that exports home directory data from a locally mounted directory `/global/local-fs/nfs/export/home`. The example assumes the following:

- The mount point `/global/local-fs/nfs` is used to mount a UFS local file system on an Oracle Solaris Cluster global device partition.
- The `/etc/vfstab` entry for the `/global/local-fs/nfs` file system should omit the `global` option and specify that the mount at boot flag is `no`.
- The path-prefix directory is on the root directory of the same file system that is to be mounted, for example, `/global/local-fs/nfs`. The path-prefix directory is the directory that HA-NFS uses to maintain administrative information and status information.

1. **On a cluster node, assume the `root` role or assume a role that provides `solaris.cluster.modify RBAC` authorization.**
2. **Determine whether the `HASStoragePlus` resource type and the `SUNW.nfs` resource type are registered.**

The following command prints a list of registered resource types.

```
# clresourcetype show | egrep Type
```

3. **If necessary, register the `HASStoragePlus` resource type and the `SUNW.nfs` resource type.**

```
# clresourcetype register SUNW.HASStoragePlus
# clresourcetype register SUNW.nfs
```

4. **Create the failover resource group `nfs-rg`.**

```
# clresourcegroup create -p PathPrefix=/global/local-fs/nfs nfs-rg
```

5. **Create a logical host resource of type `SUNW.LogicalHostname`.**

```
# clreslogicalhostname create -g nfs-rg -h log-nfs nfs-lh-rs
```

Note - If you require a fully qualified hostname, you must specify the fully qualified name with the `-h` option and you cannot use the fully qualified form in the resource name.

6. **Create the resource `nfs-hastp-rs` of type `HASStoragePlus`.**

```
# clresource create -g nfs-rg -t SUNW.HASStoragePlus \
-p FilesystemMountPoints=/global/local-fs/nfs \
-p AffinityOn=True nfs-hastp-rs
```

The resource is created in the enabled state.

Note - You can use the `FilesystemMountPoints` extension property to specify a list of one or more mount points for file systems. This list can consist of mount points for both local file systems and global file systems. The mount at boot flag is ignored by HASToragePlus for global file systems.

7. Bring online the resource group `nfs-rg` on a cluster node.

The node where the resource group is brought online becomes the primary node for the `/global/local-fs/nfs` file system's underlying global device partition. The file system `/global/local-fs/nfs` is then mounted on this node.

```
# clresourcegroup online -M nfs-rg
```

8. Create the resource `nfs-rs` of type `SUNW.nfs` and specify its resource dependency on the resource `nfs-hastp-rs`.

The file `dfstab.nfs-rs` must be present in `/global/local-fs/nfs/SUNW.nfs`.

```
# clresource create -g nfs-rg -t SUNW.nfs \  
-p Resource_dependencies_offline_restart=nfs-hastp-rs nfs-rs
```

The resource is created in the enabled state.

Note - Before you can set the dependency in the `nfs-rs` resource, the `nfs-hastp-rs` resource must be online.

9. Take offline the resource group `nfs-rg`.

```
# clresourcegroup offline nfs-rg
```

10. Bring online the `nfs-rg` group on a cluster node.

```
# clresourcegroup online -eM nfs-rg
```



Caution - Ensure that you switch only the resource group. Do *not* attempt to switch the device group. If you attempt to switch the device group, the states of the resource group and the device group become inconsistent, causing the resource group to fail over.

Whenever the service is migrated to a new node, the primary I/O path for `/global/local-fs/nfs` will always be online and colocated with the NFS servers. The file system `/global/local-fs/nfs` is locally mounted before the NFS server is started.

▼ How to Set Up the HASStoragePlus Resource Type for an NFS-Exported ZFS

The following procedure uses a simple NFS service.

See [“Creating a Basic ZFS Storage Pool”](#) in [“Managing ZFS File Systems in Oracle Solaris 11.2”](#) for information about how to create a ZFS pool. See [“Creating a ZFS File System Hierarchy”](#) in [“Managing ZFS File Systems in Oracle Solaris 11.2”](#) for information about how to create a ZFS file system in that ZFS pool.

1. **On a cluster node, assume the root role or assume a role that provides `solaris.cluster.modify` RBAC authorization.**
2. **Determine whether the HASStoragePlus resource type and the SUNW.nfs resource type are registered.**

The following command prints a list of registered resource types.

```
# clresourcetype list
```

3. **If necessary, register the HASStoragePlus resource type and the SUNW.nfs resource type.**

```
# clresourcetype register SUNW.HASStoragePlus SUNW.nfs
```

4. **Create the failover resource group.**

```
# clresourcegroup create -p PathPrefix=path resource-group
```

5. **Create a logical host resource of type SUNW.LogicalHostname.**

```
# clreslogicalhostname create -g resource-group \  
-h logical-hostname logicalhost-resource
```

Note - If you require a fully qualified hostname, you must specify the fully qualified name with the `-h` option and you cannot use the fully qualified form in the resource name.

6. **Create the ZFS file system resource of type HASStoragePlus.**

```
# clresource create -g resource-group -t SUNW.HASStoragePlus \  
-p Zpools=zpool HASP-resource
```

The resource is created in the enabled state.

Note - You can specify a list of one or more ZFS pools for the `Zpools` extension property.

7. **Bring online the resource group on a cluster node in a managed state.**

The node on which the resource group is brought online becomes the primary node for the ZFS file system. The ZFS pool *zpool* is imported on this node. The ZFS file system is consequently mounted locally on this node.

```
# clresourcegroup online -M resource-group
```

8. Create the resource of type `SUNW.nfs` and specify its resource dependency on the resource of type `SUNW.HAStoragePlus`.

The file `dfstab.nfs-rs` must be present in `zpool/nfs/SUNW.nfs`.

```
# clresource create -g resource-group -t SUNW.nfs \
-p resource_dependencies_offline_restart=HASP-resource NFS-resource
```

The resource is created in the enabled state.

Note - Before you can set the dependency in the `NFS-resource` resource, the `HASP-resource` resource must be online.

9. Bring online the `resource-group` group on a cluster node in a managed state.

```
# clresourcegroup online -M resource-group
```

Example 1-2 Setting Up the HAStoragePlus Resource Type for an NFS-Exported ZFS File System

The following example uses a simple NFS service. The example assumes the following:

- The `nfs/export` directory exists in the ZFS pool `/nfszpool`.
- The `dfstab.resource` file exists in the `/nfszpool/nfs/SUNW.nfs` directory.
- The path-prefix directory is on the root directory of the same file system that is to be mounted, for example, `/nfszpool/nfs`. The path-prefix directory is the directory that HA-NFS uses to maintain administrative information and status information.

```
phys-schost-1% su
Password:
# clresourcetype list
SUNW.LogicalHostname:2
SUNW.SharedAddress:2
# clresourcetype register SUNW.HAStoragePlus SUNW.nfs
# clresourcegroup create -p PathPrefix=/nfszpool/nfs nfs-rg
# clreslogicalhostname create -g nfs-rg -h log-nfs nfs-lh-rs
# clresource create -g nfs-rg -t SUNW.HAStoragePlus \
-p Zpools=nfszpool nfs-hastp-rs
# clresourcegroup online -M nfs-rg
# clresource create -g nfs-rg -t SUNW.nfs \
-p resource_dependencies_offline_restart=nfs-hastp-rs nfs-rs
```

Tuning the HA for NFS Fault Monitor

The HA for NFS fault monitor is contained in a resource whose resource type is `SUNW.nfs`.

For general information about the operation of fault monitors, see [“Tuning Fault Monitors for Oracle Solaris Cluster Data Services”](#) in [“Oracle Solaris Cluster Data Services Planning and Administration Guide”](#).

Fault Monitor Startup

The NFS resource `MONITOR_START` method starts the NFS system fault monitor. This start method first checks if the NFS system fault monitor `nfs_daemons_probe` is already running under the process monitor daemon `rpc.pmfd`. If the NFS system fault monitor is not running, the start method starts the `nfs_daemons_probe` process under the control of the process monitor. The start method then starts the resource fault monitor `nfs_probe`, also under the control of the process monitor.

Fault Monitor Stop

The NFS resource `MONITOR_STOP` method stops the resource fault monitor. If no other NFS resource fault monitor is running on the local node, the stop method stops the NFS system fault monitor.

Operations of HA for NFS Fault Monitor During a Probe

This section describes the operations of the following fault monitoring processes:

- NFS system fault monitoring
- NFS resource fault monitoring
- Monitoring of file sharing

NFS System Fault Monitoring Process

The NFS system fault monitor probe monitors the NFS daemons `nfsd`, `mountd`, `statd`, and `lockd`, and the RPC portmapper service daemon `rpcbind` on the local node. The probe checks for the presence of the process and its response to a null `rpc` call. This monitor uses the following NFS extension properties:

- `Rpcbnd_nullrpc_timeout`
- `Rpcbnd_nullrpc_reboot`
- `Statd_nullrpc_timeout`
- `Lockd_nullrpc_timeout`
- `Mountd_nullrpc_timeout`
- `Mountd_nullrpc_restart`
- `Nfsd_nullrpc_timeout`
- `Nfsd_nullrpc_restart`

See [“Setting HA for NFS Extension Properties” on page 13](#).

Each NFS system fault monitor probe cycle performs the following steps in a loop. The system property `Cheap_probe_interval` specifies the interval between probes.

1. The fault monitor probes `rpcbind`.
 - If the process terminates unexpectedly, but a warm restart of the daemon is in progress, `rpcbind` continues to probe other daemons.
 - If the process terminates unexpectedly, the fault monitor reboots the node.
 - If a null `rpc` call to the daemon terminates unexpectedly, `Rpcbnd_nullrpc_reboot=True`, and `Failover_mode=HARD`, the fault monitor reboots the node.
2. The fault monitor probes `statd` first, and then `lockd`.
 - If `statd` or `lockd` terminate unexpectedly, the system fault monitor attempts to restart both daemons.
 - If a null `rpc` call to these daemons terminates unexpectedly, the fault monitor logs a message to `syslog` but does not restart `statd` or `lockd`.
3. The fault monitor probes `mountd`.
 - If `mountd` terminates unexpectedly, the fault monitor attempts to restart the daemon.
 - If the null `rpc` call to the daemon terminates unexpectedly and `Mountd_nullrpc_restart=True`, the fault monitor attempts to restart `mountd` if the cluster file system is available.
4. The fault monitor probes `nfsd`.
 - If `nfsd` terminates unexpectedly, the fault monitor attempts to restart the daemon.
 - If the null `rpc` call to the daemon terminates unexpectedly and `Nfsd_nullrpc_restart=TRUE`, the fault monitor attempts to restart `nfsd` if the cluster file system is available.
5. If any one of the above NFS daemons (except `rpcbind`) fails to restart during a probe cycle, the NFS system fault monitor will retry the restart in the next cycle. When all the NFS daemons are restarted and healthy, the resource status is set to `ONLINE`. The monitor tracks unexpected terminations of NFS daemons in the last `Retry_interval`. When the total

number of unexpected daemon terminations has reached `Retry_count`, the system fault monitor issues a `scha_control` giveover. If the giveover call fails, the monitor attempts to restart the failed NFS daemon.

6. At the end of each probe cycle, if all daemons are healthy, the monitor clears the history of failures.

NFS Resource Fault Monitoring Process

NFS resource fault monitoring is specific to each NFS resource. The fault monitor of each resource checks the status of each shared path to monitor the file systems that the resource exports.

Before starting the NFS resource fault monitor probes, all the shared paths are read from the `dfstab` file and stored in memory. In each probe cycle, the probe performs the following steps.

1. If `dfstab` has been changed since the last read, the probe refreshes the memory.
If an error occurs while reading the `dfstab` file, the resource status is set to `FAULTED`, and the monitor skips the remainder of the checks in the current probe cycle.
2. The fault monitor probes all the shared paths in each iteration by performing `stat()` on the path.
If any path is not functional, the resource status is set to `FAULTED`.
3. The probe checks for the presence of NFS daemons (`nfsd`, `mountd`, `lockd`, `statd`) and `rpcbind`.
4. If any of these daemons are down, the resource status is set to `FAULTED`.
5. If all shared paths are valid and NFS daemons are present, the resource status is reset to `ONLINE`.

Monitoring of File Sharing

The HA for NFS fault monitor probe monitors the success or failure of file sharing by monitoring the following files:

- `/etc/dfs/sharetab`
- `/etc/mnttab`
- `Pathprefix/SUNW.nfs/dfstab.resource`

The *Pathprefix* part of the file path is the value of the `Pathprefix` extension property for the resource group, and *resource* is the resource name.

If the probe detects any modification to any of these files, it shares the paths in `dfstab.resource` again.

Upgrading the SUNW.nfs Resource Type

Upgrade the SUNW.nfs resource type if the following conditions apply:

- You upgrade the HA for NFS data service to the latest version of Oracle Solaris Cluster from an earlier version of the data service.
- You upgrade from an earlier version of the operating system.

For general instructions that explain how to upgrade a resource type, see [“Upgrading a Resource Type”](#) in [“Oracle Solaris Cluster Data Services Planning and Administration Guide”](#). The information that you require to complete the upgrade of the resource type is provided in the subsections that follow.

Information for Registering the New Resource Type Version

The release of Oracle Solaris Cluster data services indicates the release in which the version of the resource type was introduced.

To determine the version of the resource type that is registered, use the `clresourcetype show` command.

The resource type registration (RTR) file for this resource type is `/opt/SUNWscnfs/etc/SUNW.nfs`.

Information for Migrating Existing Instances of the Resource Type

The information that you require to edit each instance of the resource type is as follows:

- You must perform the migration when the resource group is in an unmanaged state.
- For Oracle Solaris Cluster 4.0, the required value of the `Type_version` property is 3.3.

The following example shows a command for modifying an instance of the SUNW.nfs resource type.

EXAMPLE 1-3 Migrating Instances of the SUNW.nfs Resource Type

```
# clresource set -p Type_version=3.3 nfs-rs
```

This command modifies the `Type_version` property of the `nfs-rs` resource to 3.3.

HA for NFS Extension Properties

This section describes the extension properties for the resource type `SUNW.nfs`. This resource type represents the Network File System (NFS) application in an Oracle Solaris Cluster configuration.

For details about system-defined properties, see the [r_properties\(5\)](#) man page and the [rg_properties\(5\)](#) man page.

The extension properties of the `SUNW.nfs` resource type are as follows:

`Lockd_nullrpc_timeout`

The time-out value (in seconds) to use when probing `lockd`

Data type	Integer
Default	120
Range	Minimum = 60
Tunable	At any time

`Monitor_retry_count`

The number of times that the process monitor facility (PMF) restarts the fault monitor during the time window that the `Monitor_retry_interval` property specifies. Note that this property refers to restarts of the fault monitor itself, rather than the resource.

Data type	Integer
Default	4
Range	0 – 2,147,483,641 A value of –1 indicates an infinite number of restart attempts.
Tunable	At any time

Monitor_retry_interval

The time (in minutes) over which failures of the fault monitor are counted. If the number of times that the fault monitor fails is more than the value that is specified in the extension property Monitor_retry_count within this period, the PMF restarts the fault monitor.

Data type	Integer
Default	2
Range	0 – 2,147,483,641 –1 indicates an infinite amount of time.
Tunable	At any time

Mountd_nullrpc_restart

A Boolean to indicate whether to restart mountd when a null rpc call fails.

Data type	Boolean
Default	True
Range	Not applicable
Tunable	At any time

Mountd_nullrpc_timeout

The time-out value (in seconds) to use when probing mountd.

Data type	Integer
Default	120
Range	Minimum = 60
Tunable	At any time

Nfsd_nullrpc_restart

A Boolean to indicate whether to restart nfsd when a null rpc call fails.

Data type	Boolean
Default	False
Range	Not applicable

Tunable At any time

Nfsd_nullrpc_timeout

The time-out value (in seconds) to use when probing nfsd.

Data type Integer

Default 120

Range Minimum = 60

Tunable At any time

Rpcbind_nullrpc_reboot

A Boolean to indicate whether to reboot the system when a null rpc call on rpcbind fails.

Data type Boolean

Default False

Range Not applicable

Tunable At any time

Rpcbind_nullrpc_timeout

The time-out value (in seconds) to use when probing rpcbind.

Data type Integer

Default 120

Range Minimum = 60

Tunable At any time

Statd_nullrpc_timeout

The time-out value (in seconds) to use when probing statd.

Data type Integer

Default 120

Range Minimum = 60

Tunable At any time

Index

A

automountd daemon, 11

C

changing share options, 23, 25
configuring HA for NFS, 18

E

extension properties
SUNW.nfs resource type, 37

F

fault monitor
operation, 32
startup, 32
stops, 32
files
RTR, 35

G

global zone, 9

H

HA for NFS
fault monitor, 32
installing, 12
registering and configuring, 18

software package, installing, 12
task map, 10
tuning method timeouts, 26

I

installing
HA for NFS, 12

L

loopback file system (LOFS), restrictions with, 11

M

method timeouts
HA for NFS, 26

N

non-global zones
restriction, 9

O

Oracle Solaris Cluster software
publisher, 12, 12

P

package, 12

planning installation and configuration, 10
properties, 35
 See also extension properties
 Type_version, 35
publisher
 Oracle Solaris Cluster software, 12, 12
restriction, 9

R

registering HA for NFS, 18
resource type registration (RTR) file, 35
resource type upgrade, 35
restrictions
 loopback file system (LOFS), 11
 Service Management Facility, 10
 ZFS, 11
 zones, 9
RTR (resource type registration) file, 35

S

Service Management Facility, restrictions with, 10
share options
 changing, 23, 25
software package, 12
SUNW.nfs resource type
 extension properties, 37

T

task map
 HA for NFS, 10
Type_version property, 35

U

upgrading the resource type, 35

Z

ZFS, restrictions with, 11
zones